







Log In

LOG IN / REGISTER NOTE

When the application does not recognize an account for a user, it may be that the user has an account but has changed phones, has resubscribed to the app, or so on. The log in flow allows the user to reestablish their account.


**MovieMaker
LOG IN**


User name:


Password:


Help

BACKOK









View & Rate Videos 1 Alternate

NOTE

Over time, we may have end up with too many categories to show all of them on the View & Rate Menu. In that case, we will need the ability to go to a separate, paging More Categories menu.

Only the affect portions from View & Rate 1 are shown: the modified View & Rate Menu and the new More Categories Menu.

MovieMaker
View & Rate Videos

[see menu below]

BACKSELECT

MovieMaker
More Videos

[see menu below]

BACKSELECT

---All Videos-----
Most Watched
Top Rated
Newest
Contest Winners
---Contests-----
<contest>
<contest>
<contest>
<contest>
---Categories-----
<category>
<category>
<category>
More...
---More-----
Search

<category>
<category>
<category>
<category>
<category>
<category>
<category>
<category>
More...


Initial Menu Page


Previous...
<category>
<category>
<category>
<category>
<category>
<category>
<category>
<category>
More...

Intermediate Menu Page(s)

Previous...
<category>
<category>
<category>
<category>
<category>
<category>
<category>
<category>

Final Menu Page





Share Video

MovieMaker
SHARE VIDEO

< >

<video title>
<artist name>

<category>
<category>
<category>
<category>
<category>
<category>

BACKOK


OK

MovieMaker
VIDEO SHARED!

Your video has been
entered in <category>.


OK

OK



NOTE
Share Video can be called from various popup menus. When done, return to the screen from which the user chose Share Video.

Send Video





NOTE

Send Video can be called from various popup menus. When done, return to the screen from which the user chose Send Video.

Generic Upload


NOTE Generic Upload is used to upload videos, clips, and photos.



Video Upload

NOTE

Video Upload is used ONLY to upload videos, for community categories or featured contests.






Upload from phone

Picture Message

Email

Website



Main Menu

Return to screen
from which
Upload Video was
called

Upload Help


NOTE

These help screens are used by both the Generic Upload and Video Upload sections.




OK

Return to screen
from which Picture
Message Help was
called



OK

Return to screen
from which Email
Help was called



OK

Return to screen
from which
Website Help was
called

Camera

MovieMaker
CAMERA

Take a Video
Take a Photo

BACK SELECT

MovieMaker
TAKE VIDEO

You will next use your phone's camera to take a video. Press RECORD to start recording, then press DONE to stop.

BACK OK

MovieMaker

<camera view>

CANCEL RECORD

MovieMaker

<camera view>

CANCEL DONE

NOTE
This camera menu appears only if the user's phone can take both videos and still photos. If it can only take photos, skip this menu and go straight to the Take Photo Screen.

MovieMaker
TAKE PHOTO

You will next use your phone's camera to take a photo. When you press CAPTURE, hold you phone very still until the hourglass goes away.

BACK OK

<video>

DELETE OK: Replay SAVE

MovieMaker

<camera video>

DELETE OK: View SAVE

MovieMaker

<camera view>

CANCEL CAPTURE

MovieMaker

<photo>

DELETE SAVE

MovieMaker
ADD TITLE & TEXT
(OPTIONAL)

Title:
<text entry area>


Description:
<text entry area>

SKIP OK

NOTE
When returning to my stuff:
If a video clip was taken, set the drop-down menu on My Clips and put the focus on the thumbnail of the new clip.
If a photo was taken, set the drop-down menu on My Photos and put the focus on the thumbnail of the new photo.


To
My Stuff


Featured Contests 1



Featured Contests 2

Open Contest, Rate Entries






Dynamic Viewers

NOTE

There are two possible viewers:

- 1) Rating-Enabled. The user can rate the video. This is used for user-submitted videos that we feature on the main menu. See Dynamic Viewer 1 on this page for this viewer.
- 2) Rating-Disabled. The user cannot rate the video. This is used for promotional, advertising, or other videos. See Dynamic Viewer 2 on the next page for that viewer.


Dynamic Viewer 1



NOTE

Rating: When the video ends, after a short 2-3 second pause (TBD), the app automatically navigates to the Rate Video Screen. The user uses the up and down keys to move the rating bar to select a rating. Pressing OK accepts the selected rating, updates the average rating, and updates the screen to its Video Rated state.

Dynamic Viewer 2




NOTE


When the video ends, after a 2-3 second pause (TBD), the app automatically goes to the <video info> Menu Screen.

Dynamic Text Item


1-Page Item



2-Page Item



3+ Page Item



Help

NOTE

For the help topic screens:
NEXT goes to the next topic.
PREV goes to the previous topic.
OK returns to the Help Menu.

**MovieMaker
HELP**

[see menu to side]

Using MovieMaker
View & Rate Videos
Contests
Making Videos
Uploading Videos
Using the Camera
My Account
More Support
About MovieMaker

Tentative Help Menu,
actual help topics to be
determined later

MAIN MENU


SELECT

MAIN MENU

To
Top Level,
Main Menu

NOTE

Help will have detailed
instructions on how the
various ways users can
upload videos (and
photos) into the
application. Possibly,
there will multiple help
screens on this.



Miscellaneous Items

NOTE

See the UI Conventions and the Misc Screens specs for details. Also note that screen-specific errors are detailed in the screen specs and not the flows

[underlying screen]

Sending Data...

Sending Data Message

[underlying screen]

Downloading...

Downloading Message

[underlying screen]

ERROR

<error message>

<error message>

<error message>

<error message>

<error message>

[LSK LABEL]

[RSK LABEL]

Error Popup Template

[underlying screen]

NETWORK ERROR

Network not responding. Please try again in a moment.

CANCEL

RETRY

Network Error

[underlying screen]

SERVER ERROR

An error occurred on the server. Please try again in a moment.

CANCEL

RETRY

Server Error

[underlying screen]

OUT OF MEMORY

Your phone has run out of memory and [MovieMaker] must quit to free memory. Please restart the application.

OK

Fatal Memory Error

[underlying screen]

LOW MEMORY

Your phone is low on memory and cannot perform the selected operation. You can quit [MovieMaker] to free memory and then restart the application.

CANCEL

QUIT

Low Memory Error

[underlying screen]

PHOTO CAMERA NOT FOUND

Your phone does not support the use of the camera from within this application. For more info, see Main Menu -> Help -> Using the Camera.

OK

Photo Camera Error

[underlying screen]

VIDEO CAMERA NOT FOUND

Your phone does not support the use of the camera from within this application. For more info, see Main Menu -> Help -> Using the Camera.

OK

Video Camera Error

[underlying screen]

NO AUDIO

The audio on your phone is turned off or set to vibrate. You will not be able to hear sound in [MovieMaker] until you turn the phone's audio on.

OK

No Audio Warning